


Steps for running the D70Reader command line program on Windows XP:

- Download the program by going here:

<http://home.comcast.net/~jonathan.oman/d70/index.html>

- Use Windows Explorer to display the directory you downloaded the ZIP file to:


Start->All Programs->Accessories->Windows Explorer



- Right click on 'd70reader.zip', and select 'Extract All...':




- Navigate to the d70reader directory from within Windows Explorer:




- Open a Command Prompt by doing this:

start->All Programs->Accessories->Command Prompt



- At the prompt, type 'path' (without single quotes) and then press the Enter key:



```

C:\ Command Prompt
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.


P:\Documents and Settings\Jon Oman>path
PATH=P:\WINDOWS\system32;P:\WINDOWS;P:\WINDOWS\System32\Wbem;c:\exe;c:\exe\windi
ff;c:\exe\pfe

P:\Documents and Settings\Jon Oman>

```

This displays the directories that the operating system searches for executable program files.

- Use Windows Explorer, or a Command Prompt to copy the 'd70reader.exe' file into one of the directories in the path statement:



```


C:\ Command Prompt
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

P:\Documents and Settings\Jon Oman>path
PATH=P:\WINDOWS\system32;P:\WINDOWS;P:\WINDOWS\System32\Wbem;c:\exe;c:\exe\windi
ff;c:\exe\pfe

P:\Documents and Settings\Jon Oman>copy F:\Share\D70\d70reader\d70reader.exe P:\
WINDOWS

```

Now, whenever you open a Command Prompt window, you can run the 'd70reader.exe' program, no matter what directory you are in:



```
C:\ Command Prompt - d70reader.exe
P:\Documents and Settings\Jon Oman>d70reader.exe
D70Reader - Version 0.07 - Sat Jan 1 17:04:36 UTC 2005

This is a Freeware program, use at your own risk.

This program only works with Nikon D70 image files.
(It will work with NEF/RAW and JPG files.)


Check here for latest version:
http://home.comcast.net/~jonathan.oman/d70/index.html

Format:
    d70reader [-h!-v!-w!-x] image_file_name
    d70reader [-h!-v!-w!-x] *.NEF *.JPG

    -h = this screen
    -v = verbose (raw data)
    -w = generate html table
    -x = generate xml tree

Press <Enter> to Continue
```

- Now, using the Command Prompt, navigate to one of your image directories:



```
C:\ Command Prompt
P:\Documents and Settings\Jon Oman>
F:\>cd NikonD70Images0002\12162004_0001
F:\NikonD70Images0002\12162004_0001>
```

- To see a listing of your image files, do this:

```
C:\ Command Prompt
P:\Documents and Settings\Jon Oman>f:
F:\>cd NikonD70Images0002\12162004_0001
F:\NikonD70Images0002\12162004_0001>dir_
```

When you press the Enter key you will see something like this:

```
C:\ Command Prompt
12/16/2004 02:51 PM          5,435,271 DSC_0051.NEF
12/16/2004 02:52 PM          5,545,845 DSC_0052.NEF
12/16/2004 02:52 PM          5,555,814 DSC_0053.NEF
12/16/2004 02:55 PM          5,362,643 DSC_0054.NEF
12/16/2004 02:56 PM          5,403,480 DSC_0055.NEF
12/16/2004 03:02 PM          5,540,683 DSC_0056.NEF
12/16/2004 03:03 PM          5,531,255 DSC_0057.NEF
12/16/2004 03:04 PM          5,584,219 DSC_0058.NEF
12/16/2004 03:05 PM          5,732,390 DSC_0059.NEF
12/16/2004 03:07 PM          5,684,484 DSC_0060.NEF
12/16/2004 03:08 PM          5,401,084 DSC_0061.NEF
12/16/2004 03:09 PM          5,810,406 DSC_0062.NEF
12/16/2004 03:09 PM          6,004,739 DSC_0063.NEF
12/16/2004 03:09 PM          6,019,415 DSC_0064.NEF
12/16/2004 03:10 PM          6,146,451 DSC_0065.NEF
12/16/2004 03:10 PM          6,284,985 DSC_0066.NEF
12/16/2004 03:11 PM          6,199,255 DSC_0067.NEF
12/16/2004 03:11 PM          6,192,930 DSC_0068.NEF
12/16/2004 03:13 PM          5,952,489 DSC_0069.NEF
12/16/2004 03:15 PM          5,828,473 DSC_0070.NEF
12/16/2004 03:17 PM          5,764,686 DSC_0071.NEF
       71 File(s)      401,513,179 bytes
        2 Dir(s)  26,949,345,280 bytes free

F:\NikonD70Images0002\12162004_0001>
```

- Now, you can dump the EXIF data from one of the image files by doing this:



```
Command Prompt
12/16/2004 02:51 PM      5,435,271 DSC_0051.NEF
12/16/2004 02:52 PM      5,545,845 DSC_0052.NEF
12/16/2004 02:52 PM      5,555,814 DSC_0053.NEF
12/16/2004 02:55 PM      5,362,643 DSC_0054.NEF
12/16/2004 02:56 PM      5,403,480 DSC_0055.NEF
12/16/2004 03:02 PM      5,540,683 DSC_0056.NEF
12/16/2004 03:03 PM      5,531,255 DSC_0057.NEF
12/16/2004 03:04 PM      5,584,219 DSC_0058.NEF
12/16/2004 03:05 PM      5,732,390 DSC_0059.NEF
12/16/2004 03:07 PM      5,684,484 DSC_0060.NEF
12/16/2004 03:08 PM      5,401,084 DSC_0061.NEF
12/16/2004 03:09 PM      5,810,406 DSC_0062.NEF
12/16/2004 03:09 PM      6,004,739 DSC_0063.NEF
12/16/2004 03:09 PM      6,019,415 DSC_0064.NEF
12/16/2004 03:10 PM      6,146,451 DSC_0065.NEF
12/16/2004 03:10 PM      6,284,985 DSC_0066.NEF
12/16/2004 03:11 PM      6,199,255 DSC_0067.NEF
12/16/2004 03:11 PM      6,192,930 DSC_0068.NEF
12/16/2004 03:13 PM      5,952,489 DSC_0069.NEF
12/16/2004 03:15 PM      5,828,473 DSC_0070.NEF
12/16/2004 03:17 PM      5,764,686 DSC_0071.NEF
71 File(s)      401,513,179 bytes
2 Dir(s) 26,949,345,280 bytes free
F:\NikonD70Images0002\12162004_0001>d70reader DSC_0071.NEF
```

When you press the Enter key, you should see something like this:

```
Command Prompt
12/16/2004 02:55 PM      5,362,643 DSC_0054.NEF
12/16/2004 02:56 PM      5,403,480 DSC_0055.NEF
12/16/2004 03:02 PM      5,540,683 DSC_0056.NEF
12/16/2004 03:03 PM      5,531,255 DSC_0057.NEF
12/16/2004 03:04 PM      5,584,219 DSC_0058.NEF
12/16/2004 03:05 PM      5,732,390 DSC_0059.NEF
12/16/2004 03:07 PM      5,684,484 DSC_0060.NEF
12/16/2004 03:08 PM      5,401,084 DSC_0061.NEF
12/16/2004 03:09 PM      5,810,406 DSC_0062.NEF
12/16/2004 03:09 PM      6,004,739 DSC_0063.NEF
12/16/2004 03:09 PM      6,019,415 DSC_0064.NEF
12/16/2004 03:10 PM      6,146,451 DSC_0065.NEF
12/16/2004 03:10 PM      6,284,985 DSC_0066.NEF
12/16/2004 03:11 PM      6,199,255 DSC_0067.NEF
12/16/2004 03:11 PM      6,192,930 DSC_0068.NEF
12/16/2004 03:13 PM      5,952,489 DSC_0069.NEF
12/16/2004 03:15 PM      5,828,473 DSC_0070.NEF
12/16/2004 03:17 PM      5,764,686 DSC_0071.NEF
       71 File(s)      401,513,179 bytes
       2 Dir(s)  26,949,345,280 bytes free

F:\NikonD70Images0002\12162004_0001>d70reader DSC_0071.NEF

D70ReaderProgramVersion : 0.07
Filename                  : DSC_0071.NEF
Make                      : NIKON CORPORATION
Model                    : NIKON D70
Orientation                : Horizontal (normal)
Software                  : Ver.1.02
ExposureTime              : 1/250 seconds
FNumber                   : 9.000000
ExposureProgram           : Aperture-priority AE
DateTimeDigitized         : 2004:12:16 15:17:13
ExposureBiasValue         : 0.000000
MeteringMode              : Multi-segment
Flash                     : No Flash
FocalLength               : 18
UserComment               :
FocalLengthIn35mmFilm     : 27
ISOUsed                   : 200
Quality                   : RAW
FocusMode                 : AF-S
FlashSetting              : NORMAL
FlashMode                 :
ISO-2                     : 200
ToneCompensation          : AUTO
LensType                  : G
Lens                     : 18-70mm f/3.5-f/4.5
LensInfo                  : 40 01 0c 00
ColorMode                 : MODE1a
LightSource               : NATURAL
NoiseReduction            : OFF
ShutterCount              : 1668
ImageOptimization         : NORMAL
Saturation                : NORMAL
VariProgram               :

F:\NikonD70Images0002\12162004_0001>
```

- Try the various options.